

3.5.2 Set Database Properties

Step 2: Set Database Properties for Hivedata Tables

As stated earlier each i2b2 database schema has a corresponding directory that contains the data files for installing the data. Each of these directories has a file called **db.properties** and it needs to be updated with your environment variables.

Steps for setting database properties

Assumptions:

- You are logged into the command line application for your environment. (*Linux: Terminal or Shell and Windows: Command Prompt*)
- You have already changed your working directory to the one that is appropriate for this installation.

1. At the command prompt type the following:

Linux Command

```
open db.properties
```

Windows Command

```
db.properties
```

2. The **db.properties** file will open. Set the following properties for the DBMS at your site:



Important

When setting the database properties make sure you set the user to **i2b2hive**. Projects are not assigned to Hivedata which is why the db.project property is not in the hive's db.properties file.

Database Properties File

Oracle Database

```
db.type=oracle  
db.username=i2b2hive  
db.password=demouser  
db.server=LocationOfYourDatabase:1521:xe  
db.driver=oracle.jdbc.driver.OracleDriver  
db.url=jdbc:oracle:thin:@LocationOfYourDatabase:1521:xe
```

PostgreSQL Database

```
db.type=postgresql  
db.username=i2b2hive  
db.password=demouser  
db.driver=org.postgresql.Driver  
db.url=jdbc:postgresql://LocationOfYourDatabase/i2b2?searchpath=i2b2hive
```

SQL Server Database

```
db.type=sqlserver  
db.username=i2b2hive  
db.password=demouser  
db.driver=com.microsoft.sqlserver.jdbc.SQLServerDriver  
db.url=jdbc:sqlserver://LocationOfYourDatabase:1433;database=demo
```

3. Save the changes and close the file.



Tip

To save yourself steps, DO NOT close your Command Prompt window as you will be continuing to use it throughout the remainder of the installation.