Logic Workflow

In this example walkthrough you will see how to set up a SHRINE i2b2 user with the correct roles, and set up for Active Directory Sync by calling the web services of the PM Cell.

Step	Logic	PHP	XML	Example PHP Call
1	Check that a user is not already registered in SHRINE project	get_role()	<pm: get_role>	`i2b2_get_role($user_name,$config_start_project_id)`
2	Set the user in the i2b2 SHRINE project	set_user()	<pm: set_user>	`i2b2_set_user($user_name, $full_name, $email, "", "")`
3	Give the user role of DATA_AGG	set_role()	<pm: set_role>	`i2b2_set_role($user_name, 'DATA_AGG', $config_start_project_id)`
4	Give the user role of USER	set_role()	<pm: set_role>	`i2b2_set_role($user_name, 'USER', $config_start_project_id)`
5	Set the user param of authentication_method to NTLM	set_user_param()	<pm: set_user_param>	`i2b2_set_user_param($user_name, "authentication_method", "T", "NTLM")`
6	Set the user param of domain to your AD domain	set_user_param()	<pm: set_user_param>	`i2b2_set_user_param($user_name, "domain", "T", $config_AD_Domain)`
7	Set the user param of domain_controller to the address of your domain controler	set_user_param()	<pm: set_user_param>	`i2b2_set_user_param($user_name, "domain_controller", "T", $config_domain_controler)`